Instructions for Installing AusLCI Database

Step 1: download the file and restore it

The download location is always on the Lifecycles website - under Products > Databases > AusLCI Database section.

https://www.lifecycles.com.au/life-cycle-assessment-databases

Save the file on your desktop or somewhere easy to remember. Don't save it into your Simapro database directory as this will stop it being able to unpack to that directory. Also don't save to a USB stick or external drive – as this will restrict or slow down the unpacking.

To unpack this file – open SimaPro and select menu item **File > Database management > Restore**. Select the backup file from your where you downloaded the file.

When the restore dialogue opens, select the location – your default location will normally appear and this is fine to use, then press save.

Be careful not to click on one of your existing library names shown inside the dialogue, as this will make the restored file overwrite your file.

When the database is restored – don't open it¹; you want to open your main database which contains you other libraries and projects.



Confirm	×
?	Restore is ready (SimaPro database: "C:\Users\tim\Dropbox (LCS)\Public\AusLCI_2016_04_08"). Do you want to open this database?
	Yes

¹ If you do open it, its fine, just close it again.

Step 2: Import AusLCI data into your main database data

Open your existing database (usually "Professional" or something you renamed the database to).



You will get a scary message about how this will replace existing data and change results as shown below. Select **Yes**



Browse Select the database to be imported AusLCI202X_XXX XX (with the date of the AusLCI release) and press open.

<u> </u>				
Projects	General objects			
Projects			Libraries	
Select Nan	ne	A Protect	Select Name	∠ Protect
Open databas	se		×	
Open databas	e local server	· · ·	- D X	
Open databas rver cation	e local server S:\Database\		- □ × <u>•</u> <u>Open</u> • <u>C</u> ancel	-

Select the two AusLCI libraries to import by clicking in the checkboxes. Also check the 'Delete empty process categories' check box. This will help clean up redundant subcategories in the SimaPro library as these have been changed as the database has been updated.

's Import SimaPro Database									
Location and name of import database S:\Database\AusLCI\AusLCI_V1_39_InEI22								<u>B</u> rowse	
Projects General objects									
Projects				Libraries					
Select	Name	$-\Delta$	Protect	S	elect	Name	Δ	Protect	
						AusLCI System Processes			
						AusLCI Unit Processes			
4									
	include library items used in coloctor							/	
 Only include library-items used in selected Delete empty process categories 									
Select A	II	\langle	<u>l</u> mı	ро	rt	\supset		C <u>l</u> ose	

Click the Import button. SimaPro will undertake a series of checks.

After a series of checks in which you are asked to accept replacements, the library should import.

If there are import errors, email <u>lifesupport@lifecycles.com.au</u> or call lifecycles on 03 9417 1190.